

How to change the Timbuktu Pro contact port on Windows Operating system

Note: This guide requires that you edit your registry. The registry contains files and setting that are crucial to the running of Windows and if damaged or misconfigured, could cause severe problems. Please be sure to back up your registry before making changes.

Note: Changing the TCP contact port is only supported on Timbuktu for Windows version 8.0.1.1201 and later.

1. Open up your Registry Editor window and navigate to the Ports Key.
 - Click Start >> Run
 - Type: regedit
 - Click ok
 - Navigate to:

HKEY LOCAL MACHINE\Software\Netopia\Timbuktu Pro\Security\Ports

2. Create a new key called "TCP" (with out the quotes).
 - Click Edit in the menu bar
 - Mouse over New
 - Select Key
 - Name it TCP
3. Create a DWORD value inside the TCP key, with the name "ContactStream" and set the value to something other then 0 (ie: 408, 409, 1843)
 - Click Edit in the menu bar
 - Mouse over New
 - Select DWORD Value
 - Name it ContactStream
 - Double Click the new DWORD to modify
 - Set Base to "Decimal"
 - Enter the port number in the "value data" field
 - Click ok
 - Close Regedit

Note: Timbuktu will need to be shut down and restarted in order for this change to take.

Example: ContactStream=408